

# Step-by-Step Guide to Setting Up Your Microphone in Chrome, Edge, Firefox, and Safari

## ✅ 1. Initial Microphone Check in the Operating System

### On Windows:

1. Right-click on the **speaker icon** in the taskbar.
2. Select "**Sound settings**".
3. Scroll down to the "**Input**" section.
4. Choose your preferred microphone from the dropdown menu.
5. Speak into the microphone — the volume indicator should move.

### 🍏 On macOS:

1. Go to **System Preferences > Sound > Input**.
2. Select the desired microphone from the list.
3. Speak and check if the input level bar responds.

---

## ✅ 2. Microphone Check and Selection in the Browser

---

### 🌐 Google Chrome

1. Open Chrome.
2. Connect to **SkillGym**, launch a simulator in **push-to-talk mode** and press the **button** to speak.
3. When prompted, click "**Allow**".
4. Click the **lock icon** 🗝️ in the address bar.
5. Go to **Site settings**.
6. In the **Microphone** section, choose the correct device from the dropdown list.
7. Refresh the page if needed.

### 📌 To manage microphone settings globally:

- Visit <chrome://settings/content/microphone>
- Select your default microphone.

---

## Microsoft Edge (Chromium-based)

1. Follow the same steps as in Chrome:
  - Click the **lock icon** > **Permissions for this site**.
  - Edit the **Microphone** setting.
2. Or go directly to: <edge://settings/content/microphone>

---

## Mozilla Firefox

1. Open Firefox
2. Connect to **SkillGym**, launch a simulator in **push-to-talk mode** and press the **button** to speak.
3. When prompted, click "**Allow**".
4. To change the microphone:
  - Click the **lock icon**  > **More information** > **Permissions**.
  - Or go to <about:preferences#privacy>
  - Under **Permissions**, find **Microphone** and click **Settings...**
  - Select the correct microphone for each website.

---

## Safari (macOS)

1. Open Safari
2. Connect to **SkillGym**, launch a simulator in **push-to-talk mode** and press the **button** to speak.
3. When prompted, select "**Allow**".
4. To change preferences:
  - Go to **Safari** > **Settings for This Website...**
  - Set **Microphone** to **Allow** or **Ask**.
5. Safari uses the microphone selected in the Mac's System Preferences (see section 1).

---

### 3. Final Test

Go to <https://webcammictest.com/check-microphone.html> or any app that uses a microphone and check that:

- The selected microphone is active.
- The sound level bar reacts to your voice.
- The browser is not blocking access.

---

### General Tips

- Make sure your **browser is up to date**.
- If the microphone doesn't work:
  - Try unplugging and reconnecting it.
  - Restart the browser or the computer.
  - Make sure **no other app is using it** (e.g., Teams, Zoom).